

STEP 1

- Under chooser, select LaserWriter 8.7

STEP 2 PRINT/DOCUMENT

- Print one page at a time. Enter page range here.
- Separations: Off
- Registration: Centered
- Bleed: .125"
- Offset: 12 pt

Custom Bleed Xtension adds a new tab called Bleed to the Print dialog box.

Select a Custom bleed type, check Clip to Bleed Limits, and enter .125" for all four sides. Offset remains under the Document tab in the Print dialog box.

Quark CMS Xtension should be deactivated and should not have added a new tab to the Print dialog box. Turn it off under the Edit menu/Preferences/Color Management.

STEP 3 PRINT/SETUP

- Printer Description: Acrobat Distiller
- Paper Size: Custom
- Paper Width & Height: enter a dimension 1" wider and higher than your trim size to compensate for the inclusion of marks and bleeds.
- Paper Offset & Gap: 0"

STEP 4 PRINT/OUTPUT

- Print Colors: Composite Color
- Halftoning: Printer
- Resolution: 2400

STEP 5 PRINT/OPTIONS

- Output: Normal
- Data: Binary
- OPI: Include Images
- Overprint EPS Black: Off
- Full Resolution TIFF Output: On

STEP 6 PRINTER BUTTON / GENERAL

- Click Printer button on bottom of Print Window
- Destination: File
- Enter page range to print single page

STEP 7 SAVE AS FILE

- PostScript Level: Level 2 and 3
- Data Format: Binary
- Font Inclusion: All

